


PowerDRAW

**A Powerful Graphic Generation
Program for the TRS-80™**

**Create screen graphics
that you can merge with
your programs. Mix text
and graphics easily!**



POWERSOFT

PRODUCTS FROM BREEZE/QSD, INC

17060 DALLAS PKWY.
SUITE 114
DALLAS, TEXAS 75248

NOTICE OF DISCLAIMER

This software is sold on an AS-IS basis only and Breeze/QSD, Inc., shall not be liable for any damages, whether real or alleged, arising from the use of this software. Breeze/QSD warrants the media on which this software is supplied to be free of defect for a period of 30 days after purchase. Breeze/QSD further warrants that the software will do what it has been advertised to do, however, determination of suitability for any particular purpose is the sole responsibility of the end user.

Copyright ©1982 by Breeze/QSD, Inc.

All rights reserved. No part of this software or the associated documentation may be reproduced in part or in whole, by any means including but not limited to the use of electronic, electromagnetic, optical, xerographic, network or BBS information and retrieval systems without the express written consent of Breeze/QSD, Inc. The end user is permitted to make copies of this software for backup and/or archival purposes ONLY. Unauthorized use, copying, adaptation or distribution of this software is a violation of United States copyright laws and is strictly prohibited. Violators are subject to civil penalties and/or criminal prosecution.

Power**DRAW**

A graphics generation system for the TRS-80™



A PowerSOFT Product from
Breeze/QSD Incorporated
17060 Dallas Pkwy, Suite 114
Dallas TX 75248
214/733-4475

INTRODUCTION

PowerDRAW is a highly sophisticated graphic screen editor written by Kim Watt, author of **SUPER UTILITY PLUS** and other major programs. Graphics and Text may be intermixed. A Screen may be saved to any of several available memory buffers. Buffers may be saved to tape or disk in one of six available formats. Single and Double wide video are supported. Mod I and III are both supported. A Trace mode may be activated to constantly display cursor positioning on the screen. A Grid mode may be activated to aid in centering your figures on the screen. **PowerDRAW** also supports the Alpha Products(tm) joystick. (If using the joystick, and you have the new version, set the switch setting to 5).

LOADING THE PROGRAM:

PowerDRAW is supplied as a /CMD file on a special transfer disk. To move the files onto your own disk, format a destination disk using **TRSDOS** (2.3 for Model I, or 1.3 for Model III). If you have two or more drives, place the freshly formatted disk in drive 1. Place the **PowerDRAW** disk in drive 0 and press the **RESET** button on your computer. This will load a special transfer program and you will be shown the files on the disk. You will also be asked for a destination drive. Supply the drive number where the destination disk is and press **ENTER**.

Once you have **PDRAW/CMD** on your diskette, from **DOS READY**, type **PDRAW**. After a short loading period the menu of options will appear on your screen. **PowerDRAW** makes calls through **DOS** to load and save disk files, therefore your **DOS** system diskette must remain in Drive 0 if any disk I/O is used. **PowerDRAW** is compatible with all major **DOS**'s available on both the Model's I and III.

The following will explain in detail the various commands available while running **PowerDRAW**.

From DOS READY, type PDRAW to load PowerDRAW into memory. ROM is checked to determine if the program is running in a Mod I or III, and therefore only one version of the program is needed for both machines. Top of Memory is honored on both machines (4049H Mod I, 4411H Mod III), and anything above will not be disturbed. After PowerDRAW is loaded, the menu will be displayed on your screen. Press <ENTER> to proceed.

There are two MODES of operation, GRAPHICS and TEXT. Initially, you are in the GRAPHICS MODE. You will see 1 pixel flashing in the upper left corner of the screen. You may now use the arrow keys to move the cursor anywhere on the screen. The SHIFTED arrow keys will move the cursor three pixels at a time for rapid positioning. All of the routines available as displayed in the menu can be activated while pressing the corresponding letter key.

When you are in the TEXT MODE, you will see 1 character flashing in the upper left corner of the screen. Any control keys entered while in the TEXT mode must be made while holding down the CLEAR key (control key). Thus, to get the menu in the GRAPHICS mode, simply press M, but in the TEXT mode, you must HOLD DOWN the CLEAR key, and press M. Pressing M alone in the TEXT mode will enter the letter M at the cursor position. In the TEXT mode, the CLEAR arrow keys will enter the corresponding arrow symbol on the screen. Use the ARROWS to move the cursor, or the SHIFT ARROWS for rapid movement. All keys will repeat if held down.

NOTE: If a joystick is connected, it may be used interchangeably with keyboard commands to issue cursor movement commands. All 8 directions can be controlled by moving the joystick in the appropriate direction. The button on the joystick is equal to the shift key. Thus holding the joystick to the right AND pressing the button will result in the cursor moving rapidly to the right. The DRAW, SKIP and ERASE modes must be set from the keyboard.

(Remember, when in the **GRAPHICS MODE**, you may enter the **LETTER ALONE** to execute the command, but in the **TEXT MODE**, you **MUST HOLD DOWN** the **CLEAR** key while you press the letter.)

FEATURES:

A - SET ANGLES

PowerDRAW can draw lines at angles using the I,O,K,L keys. This option will allow you to set at which angle the program is to draw. First you will be shown the current setting, and asked to supply the Horizontal Angle. This is the number of HORIZONTAL pixels the cursor should move with each key press. Next you are asked to supply the Vertical Angle. This is the number of VERTICAL pixels the cursor should move with each key press. Pressing ENTER alone for either question will leave the setting unchanged. The next question will be if the lines are to be SOLID or DOTTED. This specifies whether the dots in between the start and end are to be filled or left blank.

If, for example, the Horizontal Angle is 4, and the Vertical Angle is 3, and SOLID is selected. If you now press the O key, the cursor will move 4 pixels to the right, and then 3 pixels upwards and all dots will be filled (when DRAW MODE is set as explained further). If DOTTED was selected, the cursor would make the move, but none of the in between pixels would be lit. You would, in this case, press D to draw a dot where the current cursor is. The ANGLE feature may seem complicated at first, but offers a wide variety of control and is mastered quickly with use of the program.

B - BUFFERS

There are several buffer areas available in the PowerDRAW program, each with a specific use. There is a 256 byte Input Output buffer used when loading/saving files to disk or tape. Following that, there is a 1024 byte buffer which is the current WORKSPACE. A duplicate of this buffer is what you see on the screen, and therefore, when the MENU is being

displayed, the workspace buffer can restore the screen contents. Following the workspace buffer to the top of memory are additional HOLDING buffers that may store from 1 to 34 screen images.

When the B command is executed, a display of the contents of the holding buffers is given. The buffer number, followed by an = sign will be shown for all the available buffers. If a buffer contains data, a graphics block will follow the = sign. You will then be prompted for one of six possible commands involving the buffers.

The STATUS of the buffers may be checked at any time by using the control combination CLEAR / (that is, hold down the CLEAR key and press the slash key). This will display the list of buffers on the screen. The workspace buffer will not be affected.

C - CLEAR ALL

This will load 80H (graphics blanks) into ALL holding buffers. **THERE IS NO SECOND CHANCE**, so be careful when using this option. It is recommended using this option once the first time you run the program to start with a clean slate. The contents of the workspace buffer are not affected. The cursor position is not changed, use the H command to re-home the cursor if needed.

E - EXCHANGE

This will exchange the data in the workspace buffer (the one you see on the video) with any of the holding buffers. This will serve 2 purposes. It saves the current workspace, and brings in a previously stored buffer to be operated on.

R - RECALL

This will move the contents of any of the holding buffers into the workspace buffer. The workspace buffer's previous contents will be destroyed.

S - STORE

This will save the contents of the workspace buffer to any of the holding buffers. The contents of the workspace buffer are not changed.

Z - ZERO

This command will load 80H (the code for a graphics blank) into all bytes of any SINGLE holding buffer. The workspace buffer is not affected.

M - MERGE

This command will take any specified holding buffer and merge it with the workspace buffer. This is a character orientated move. Any character locations in the holding buffer that are not 20H (space) or 80H (graphic block with all pixels off) are moved to the holding buffer.

Once you have selected any of the above commands, it will immediately be executed, and you will be return to the graphics or text entry mode you came from. If you do not wish to execute the command, then answer the prompt with ENTER or BREAK.

C - CLEAR BUFFER

This command will clear the contents of the workspace buffer. All bytes are set to 80H (graphics byte with all bits off). In order that the screen is not accidentally executed, you **MUST** enter this command **TWICE**. The second time, the **CLEAR** key **MUST** be held down. Thus, if you really want to clear the workspace buffer (the video screen), hold down the **CLEAR** key and press **C TWICE**. If the screen contents were **NOT** previously moved to a holding buffer, the data **CANNOT** be recovered.

D - DRAW MODE

When you are in the GRAPHICS sub-mode, you may move the cursor with the arrow keys. There are 3 sub-modes while in the graphics mode: **DRAW**, **SKIP**, and **ERASE**. Selecting **D** will set the **DRAW** mode. When this is set, any pixels the cursor is over will be **LIT**. Therefore, to draw a line, press **D** to set the draw mode, then use the arrow keys to move the cursor. When **D** is first pressed, the current pixel at the cursor will be lit. If you press **D** to set draw mode, then **S** to set skip mode, a single pixel will be lit.

When in the TEXT sub-mode, 2 special keys are active to **SET** and **RESET** a complete character. **SHIFT SPACEBAR** will **CLEAR** the current character, and **SHIFT 0** will **SET** the current character.

E - ERASE MODE

Similar to the above mentioned **DRAW** mode, except that pressing **E** will set the **ERASE** mode. Here any pixels the cursor is over will be turned **OFF**. When **E** is first pressed, the current pixel will be turned off. Moving the cursor over any other lit pixels will turn them off also.

F - FLASH SPEED

This option will allow you to set the speed at which the cursor flashes. You may set the speed of the GRAPHICS and TEXT sub-modes separately. Enter a number from 1 to 9 in response to the prompts.

G - GET FILE

This option allows loading the holding buffers. You are first asked if the data is to come from DISK or TAPE.

If you select DISK, you will be asked for a FILENAME. Enter the filespec in standard DOS format. A default extension of /DRW is added to your filename if one is not specified.

If you select TAPE, you will be asked one of the following questions. If the program is running in a Mod I, you will be asked if tape deck number 1 or 2 is to be used. If running in a Mod III, you will be asked to load at 500 or 1500 baud. (Mod III LDOS users be sure to load in HITAPE/CMD if you plan to use 1500 baud cassette I/O). 1500 baud works only if you are loading a COMPRESSED FORMAT file. Everything else must be 500 baud. You will then be prompted to prepare the cassette deck.

The data will then be read from the specified media. The data read in must be in COMPRESSED FORMAT (explained under the P command). If it is not, you will be issued an "Invalid File Format" message, and all buffers will remain undisturbed.

If the file is valid, the corresponding buffers will be loaded. When the file was first saved, only the buffers that HAD DATA were included. When the file is being re-loaded,

only the indicated buffers will be affected. Thus, if you have one file that contains buffers 1-5, and a second file that contained buffers 6-10, and currently in memory you have buffers 11-25, then loading BOTH files will leave buffers 11-25 undisturbed. Using this technique, you can MERGE several files. In all cases, the contents of the workspace buffer are unaffected.

H - HOME CURSOR

This option will move the cursor to the top left (starting position) of the video.

I - UP / LEFT

When in the GRAPHICS or TEXT sub-modes, this key will move the cursor up and left the number of pixels as set with the ANGLES command.

J - DISPLAY GRID

Selecting this option will toggle the GRID pattern to either the on or off states. When it is ON, a series of graphics blocks will appear on your screen. These can help you align or center your pictures.

K - DOWN / LEFT

This key moves the cursor down and left the number of pixels specified in the ANGLES command.

NOTE: When a joystick is connected, all of the cursor movements commands may be entered by moving the joystick in the appropriate direction. All 8 directions are supported.

L - DOWN / RIGHT

This key moves the cursor down and right the number of pixels specified in the **ANGLES** command.

M - MENU

Pressing this key will display the power-up menu. Press **ENTER** to resume the current mode you came from. The contents of the workspace buffer (the video) are not affected.

N - FLIP SIDES

This option will flip the right and left half of the buffer. This feature is useful when working on double wide screens, as it will bring the 'hidden' side of the buffer to the video screen.

O - UP / RIGHT

This key moves the cursor up and right the number of pixels specified in the angles command.

Remember, the HORIZONTAL moves are made first, then the VERTICAL moves. Therefore drawing a line up and left will be the opposite of drawing it down and right. Try it out to see the effect.

P - PUT FILE

This option will allow you to store the current holding buffers. First you will be asked to supply the format that you desire the data to be in. There are six options.

0 - COMPRESSED FORMAT

This will save the contents of all ACTIVE holding buffers in a minimal amount of storage space. This is the only FORMAT that may be read back in with the GET BUFFER command, so if you plan on using one of the following formats, be sure you also save it in this format for future loading. This is also the ONLY format where all the holding buffers are written out. If the file is going to disk, a default extension of /DRW is added to the filename if one is not supplied.

1 - EDAS FORMAT

This saves a file that is compatible with the EDAS editor assembler. The DB opcode is used, and 8 data bytes are stored per line for less overhead. Line numbers will start with 1, and be incremented by 1. If the data is going to disk, a default extension of /ASM is added to the filename.

2 - EDTASM FORMAT

The resulting file is compatible with the EDTASM editor assembler. The DEFW opcode is used, and 2 data bytes are stored per line for less overhead. Line numbers are the same as EDAS format. A default extension of /ASM is added to the filename if the data is going to disk.

3 - BASIC ARRAY

The resulting file will be a series of BASIC statements in which each of the 16 lines of the screen are placed into an element of a string array. The array ZZ\$ is used. It is first dimensioned (DIM ZZ\$(15)) and then each line of the screen is assigned to each element, ZZ\$(0) to ZZ\$(15). The strings are PACKED GRAPHICS. This means that you cannot use the BASIC Edit function to modify them. However you can manipulate them using the BASIC string functions, LEFT\$, MID\$ and RIGHT\$.

4 - BASIC STRING FORMAT

The file created will be loadable by BASIC. It will consist of all print statements followed by packed graphic

strings. The file is in ASCII format. A default extension of /BAS is added to a disk filename if one is not specified.

Note that you may not use the BASIC Edit function to modify these lines without altering the packed graphic strings drastically.

5 - BASIC DATA FORMAT

This file can also be loaded by BASIC. It differs from the above in the fact that the buffer bytes are put into the program in the form of DATA statements. Eight bytes are placed on each line to conserve memory. This file is also in ASCII. A default extension of /BAS is added to disk filenames.

6 - LOAD FILE FORMAT

This file will be in standard DOS load file format. The resulting file can be executed from DOS READY. The program will ORG at 3C00H (video memory), and exit is made via 402DH (back to DOS READY). A default extension of /CMD is added to disk filenames.

In option 0, compressed format, ALL the holding buffers are written out. With options 1 through 5, only A SINGLE BUFFER is selected to be written out. In ALL cases, the workspace buffer is NOT written. When writing the file to tape, and format 1 through 5 is selected, the workspace buffer is destroyed. Thus when writing to tape in non-compressed format, be sure to save the workspace buffer to one of the holding buffers. Be sure to SAVE the workspace buffer to one of the holding buffers via the B command before writing to disk or tape if you want it included.

When the above file format has been selected, you will be prompted for disk or tape. The same applies here as it does in the GET FILE instructions. Be sure to remember that the workspace buffer (the one on the video) is NOT used in the PUT BUFFERS command, and ONLY the compressed format may be re-loaded. REMEMBER, always save the workspace buffer to a holding buffer prior to ANY disk I/O.

Q - QUIT

This will terminate the program via a jump to 402DH and return to **DOS READY**. In order that you do not execute this command accidentally, you must enter it **TWICE**, the second time as a control key (see **C** command for similarity). Thus, to exit the program, hold down the **CLEAR** key, and press **Q TWICE**.

If you **STILL** accidentally exit to **DOS**, you may recover all your buffers intact as long as no memory has been disturbed above 5200H. Just **HOLD DOWN** the **R** key while the program loads in. The buffer table and the current workspace buffer will be left intact.

R - REVERSE

This command will reverse the contents of the current workspace buffer. All pixels that are **LIT**, will be turned off, and vice versa. Only **GRAPHICS** will be affected. Any **TEXT** on the screen will be left unaffected.

S - SKIP MODE

This sets the **SKIP** sub-mode while in the **GRAPHICS** **MODE**. When this is set, and pixels that the cursor moves to will be left **UNCHANGED**. (See **D** and **E** for the balance of sub-mode commands)

T - TEXT ENTRY

This toggles back and forth between the **GRAPHICS** mode and **TEXT** mode. If you are in the graphics mode, simply press **T** to enter text mode. If in text mode, you must hold

down CLEAR and press T to enter graphics mode. In text mode, all NON-CONTROL keys (CLEAR key is NOT pressed), are entered into your screen. The CLEAR ARROW keys will also enter characters. To move the cursor while in TEXT mode, ARROW moves it slowly, and SHIFT ARROW moves it quickly.

U - CURSOR POSITION

This toggles the CURSOR UPDATE option. When ON, the current location of the cursor will be displayed in the upper right hand corner of the screen. The cursor locations of the graphic and text entry modes are independent of each other. A '>' symbol will appear next to the coordinates that are currently active.

V - VIDEO WIDTH

This toggles the video width from the 64 character mode to the 32 character mode, and vice versa. The left half of the buffer in the 64 char mode will be displayed in the 32 char mode. If the cursor lies beyond the edge of the screen when changing modes, it will be repositioned.

W - WATCH BUFFERS

Selecting this option will bring all the holding buffers that are currently flagged as 'active' to the video one at a time. The current buffer number that is being displayed is shown at the top right of the screen. Press the SPACEBAR to advance to the next buffer. When all the holding buffers have been displayed, the previous screen contents will be restored and control will return to the ENTRY mode. The workspace buffer is not disturbed with this command. Press BREAK to abort this command if desired.

X - MIRROR IMAGE RIGHT / LEFT

This option will perform a mirror image reversal of the buffer ON A CHARACTER BASIS.

Y - MIRROR IMAGE TOP / BOTTOM

This option performs a mirror image reversal of the buffer ON A CHARACTER BASIS.

Z - MOVE

This option will allow you to move the contents of the buffer in any direction ON A CHARACTER BASIS. Follow this key with any of the 4 arrow keys for movement in the corresponding direction. This feature is useful in adding motion to your creations.

` - SPECIAL KEY (Shift-@)

This command is available only in the text entry mode. First, position the cursor anywhere on the video that you wish, and press CLEAR `. You will be prompted to define the area at the bottom of the screen. Two keys are required to define an area. The first key must be one of the arrows. This defines the area of the video in the corresponding direction from the current cursor location. The second key further defines the area. In addition to the arrows, two letters, A and L are acceptable as the second key.

If the two keys are UP and RIGHT arrow, then the area to the upper right from the cursor is indicated. If the entry is UP arrow and A, then ALL the screen from the cursor up

is defined. If the entry is RIGHT and L, then a LINE starting at the cursor and going to the right is indicated. Pressing the same arrow for the second entry as the first will indicate the same as A being specified. Thus RIGHT arrow RIGHT arrow is the same as RIGHT arrow A.

Once an area is defined, one of several actions may be specified:

C - CLEAR

Selection of this option will load 80H (all bits off) to the specified area.

F - FILL

This will load BFH (all bits on) to the specified area.

R - REVERSE

This will reverse (lit pixels are turned off, unlit pixels are turned on) all characters defined by the area that are graphics. Any ASCII characters in the area are not affected.

D - DUPLICATE

This will duplicate the character that the cursor is located over to all characters in the defined area.

SCREENPRINTER

Three screenprinter drivers have been provided in the program to assist you in obtaining hard-copies of your displays.

CLEAR ENTER activates the screenprinter where the bytes are printed via an internal printer driver (parallel only).

CLEAR SHIFT-ENTER will apply the needed adjustment necessary for EPSON MX-80's which have the graphics characters shifted out of their normal locations. These are the original EPSON MX-80s or those which have Grafrax-80 installed

(Those with Grafrax-Plus, or the newer FX series, cannot produce the TRS-80 block graphic characters at all).

CLEAR SPACEBAR activates the screenprinter where the bytes are printed via calls to 3BH. If any printer drivers are located in high memory, they will be called to. Press **BREAK** at any time to abort the routine.

NOTE: Your printer must be capable of printing the TRS-80 block graphics set in order for this option to function correctly. All bytes are sent to the printer **EXACTLY** as they appear in the buffer. A C/R (ascii 13) will be sent following each of the 16 video lines. If the internal driver is not being used, be aware that your printer driver may alter the bytes being sent. Be sure that your printer driver will print lower-case and graphics. **ALSO BE SURE THAT SWITCH SETTINGS ARE CORRECT.** We cannot and will not take phone calls on how to get **YOUR** printer set up. Please read your printer and/or DOS manual.

ADDITIONAL FILES:

Several additional files have been added to the diskette to aid you in incorporating your screens to your programs.

PDRAW/CMD

This is the PowerDRAW program as explained above.

PLAY/CMD

This is a utility program that will display the contents of any **COMPRESSED FORMAT** disk file you have have created. Several files may be played one after another. You may supply the filenames at the **DOS READY** command level. Example:

PLAY >3,PARTA,PARTB,PARTC

This command will display 3 files, PARTA/DRW, PARTB/DRW, and PARTC/DRW, and 3 1/8 second delays will be issued between each display screen.

If no parameters are issued with the command line, you will be asked to enter a filename(s). Enter the filenames exactly as you would have at the command level, using a comma or a space to separate the names. Entering the > symbol followed by a DECIMAL number from 0-255 will set the number of 1/8 second delays to be issued between screens (0=256). If NO delay is specified, each screen will be 'frozen' on the screen. Press SPACEBAR to advance to the next screen, or BREAK to cancel the routine.

PLAY/BAS

This is a BASIC program that will read in a SINGLE COMPRESSED FORMAT file, and display its contents to the video screen. Press ANY KEY to advance to the next screen.

There is a demo program provided on the disk and you can "PLAY" it with the following commands:

PLAY DEMO <enter>

this will "play" the pictures one at a time, using the <space bar> to advance frames. Alternatively,

PLAY >3 DEMO <enter>

this will "play" all the frames continuously with a speed setting of "3". (like a movie, of sorts)

PMERGE/CMD

This utility will merge several COMPRESSED FORMAT files together. The buffers may be overlapping, and the resulting file created may be longer than can be held in memory. If the resulting file is longer than memory can hold, then the only way it can be viewed is via one of the PLAY utilities provided. The only reason one would want to create huge files is if you want to watch a 'movie'. It is suggested that the destination file be different than the source files so they are not destroyed.

The command syntax of this program is:

PMERGE >PARTD,PARTA,PARTB,PARTC

Where PARTA/DRW, PARTB/DRW, PARTC/DRW are the source files, and PARTD/DRW is the destination file (as indicated by preceding the filename with >).

If no filenames are supplied with the dos command, you will be prompted for them. Enter the names exactly as you would at the command level, separating the names with commas or spaces.

Dear Valued TRS-80™ Customer,

If you have any questions or problems with this software package, please use the address below for ALL technical assistance. Please do not use the Dallas Parkway sales office address listed in the manual for support. That office is now ONLY for sales and shipping. There is not a technical person there. The PO Box will be picked up every Wednesday and Friday. All questions, updates, problems, etc. will be attended to at that time and mailed back to you. Because of the way the TRS-80 market has diminished, we do not have programmers on staff at all times to answer questions, like we once did. That is the way it is, unfortunately, but at least we are still here, while most other TRS-80 software houses have gone away.

Please keep in mind that we have sold thousands of these programs over the past eight years and THEY DO WORK AS ADVERTISED. If you are having difficulty, please re-read the section of the manual pertinent to the problem. If you are still having difficulties, then please feel free to write us. Include the version #'s of your DOS, screen-prints (if helpful), and a good description of your difficulty. Include any disks that may help. Also include your MASTER disk. Do NOT send your manual. Upon receipt, we will analyze your situation and try to duplicate it here, or fix it. Thank you!

PowerSoft Technical Support • PO Box 6488 • Dallas, TX 75379-6488

Dear Valued TRS-80™ Customer,

If you have any questions or problems with this software package, please use the address below for ALL technical assistance. Please do not use the Dallas Parkway sales office address listed in the manual for support. That office is now ONLY for sales and shipping. There is not a technical person there. The PO Box will be picked up every Wednesday and Friday. All questions, updates, problems, etc. will be attended to at that time and mailed back to you. Because of the way the TRS-80 market has diminished, we do not have programmers on staff at all times to answer questions, like we once did. That is the way it is, unfortunately, but at least we are still here, while most other TRS-80 software houses have gone away.

Please keep in mind that we have sold thousands of these programs over the past eight years and THEY DO WORK AS ADVERTISED. If you are having difficulty, please re-read the section of the manual pertinent to the problem. If you are still having difficulties, then please feel free to write us. Include the version #'s of your DOS, screen-prints (if helpful), and a good description of your difficulty. Include any disks that may help. Also include your MASTER disk. Do NOT send your manual. Upon receipt, we will analyze your situation and try to duplicate it here, or fix it. Thank you!

PowerSoft Technical Support • PO Box 6488 • Dallas, TX 75379-6488

PowerDRAW

**** POWER-DRAW **** version 1.6 ** by Kim Watt
(C)(p) 1981 Breeze/QSD, Inc. - Dallas, Texas

<ARROWS> move cursor

<SHIFT><ARROWS> move cursor rapidly

<LETTER> = function

<CLEAR> + <LETTER> = function in text mode

<A> = set angles

<D> = draw mode

<G> = get file

<J> = display grid

<M> = menu

<P> = put file

<S> = skip mode

<V> = video size

<Y> = mir img T/B

 = buffers

<E> = erase mode

<H> = home cursor

<K> = down / left

<N> = flip sides

<Q> = quit

<T> = text entry

<W> = watch buffers

<Z> = move

<C> = clear buffer

<F> = flash speed

<I> = up / left

<L> = down / right

<O> = up / right

<R> = reverse

<U> = cursor position

<X> = mir img L/R

<@> = special key

Key <ENTER> to continue!

*** Buffers 1-30 Available ***

01=	02=	03=	04=	05=	06=	07=	08=
09=	10=	11=	12=	13=	14=	15=	16=
17=	18=	19=	20=	21=	22=	23=	24=
25=	26=	27=	28=	29=	30=		

C>lear ALL, E>xchange, R>ecall, S>tore, Z>ero, M>erge ?

*** Saving Buffers ***.

Data in 09 buffers.

0> = Compressed

1> = EDAS

2> = EDTASM

3> = BASIC Array

4> = BASIC Strings

5> = BASIC DATA

6> = Load file

?0

D>isk or T>ape ?

Filename ?